## BENQ Camera Windows XP Installation Guide

Driver version: DC300 V5.13

• Camera model : Digital Camera 300

OS: Windows XP

• Download website: <a href="http://www.beng.com.tw/global/service/dsc/drivers.htm">http://www.beng.com.tw/global/service/dsc/drivers.htm</a>

Notice 1: These drivers are expressed to \*.zip file. Click <a href="here">here</a> to know how to install.

Notice 2: Please un-connect DC300 with PC when you install the driver.

Notice 3: If you still got Error Messages after these installation steps, please E-mail to us your problems.

## E-mail to:

Asia Pacific area and Taiwan: <a href="mailto:APFService@benq.com">APFService@benq.com</a>


America: <a href="mailto:support-sc@benq.com">support@benq-eu.com</a>
China: <a href="mailto:service@benq.com.cn">service@benq.com.cn</a>


Other Sites: <a href="mailto:IMGservice@benq.com">IMGservice@benq.com</a>

## Please specify:

- 1.OS version (WinXP)
- 2.Driver version (DC300 vX.XX)
- 3. Model No. & Serial No.
- 4. Platform spec. (Motherboard model, Platform model, Ram size, CPU spec...)
- 5.Application problem (Which steps / what situation will happen... ) & Software version
- 6. Your local Country ( Address )


Installation Step 01: Unzip DC300.zip , choose Winxp folder and click setup.exe , click Next .









Installation Step 02: Choose Language, you just could choose English or Traditional Chinese version.




## Installation Step 03: Then click Next .







Installation Step 04: Installation Completed , click Finish , system will reboot your PC automatically .




Installation Step 05: After login on Winxp , please power on DC300 then connect USB cable with PC . Launch Dsc.exe to download Picture to PC .




Installation Step 05: Also, you could check DC300 device in Device Manager.




Installation Step 06: How to launch DC300 Video mode? First, power off DC300 and then plug USB cable with PC. System will detect Video mode automatically, then launch Video .exe.




Installation Step 07: System will find New Hardware , please click next .



Installation Step 08: System will show Notice message, it's safe to click Continue Anyway to install.





Installation Step 9: Finish installation, you could launch Video.exe immediately.

