

Windows XP

0

This installation guide is only suitable for **USB driver v.1.10**, please make sure the driver you got is the specific version before you start to install the driver.

1

Power on your computer and wait until Windows has fully loaded.
(If the driver you got is from Website, please un-zip it to one floppy disk.)

2

Power on your CD-RW drive **FIRST**, and then plug the USB cable from the back of the CD-RW drive into your computer's USB port.

3

Your computer should find the new hardware and bring up the "**Found New Hardware Wizard**" window. Select the "**Install from a list or a specific location**" option and press the "**Next**" button.



4

Hit the "**Browse**" button and select "**A:\Win98&2000&XP**" where A is your floppy drive letter. Then press the "**Next**" button.



5

If you get a “**Windows Logo Testing**” box, Press the “**Continue Anyway**” to continue the installation.

Please don't concern about this warning, we already do solid testing about the new driver and it can fully compatible with XP. So please ignore the message and continue to install your driver.



6

Windows will begin copying files to your computer. When finished, press the “**Finish**” button to complete your new hardware driver installation.



7 You should now see a new drive letter under “My Computer”.

1.