JVC

Digital Photo Navigator

ENGLISH



INSTRUCTIONS

INTRODUCTION Reading this document	
Loading Still Images (Windows [®])	5
CAPTURING IMAGES Capturing still images from tape Controller window Automatic Capture Changing the transfer speed Changing the ID number ADDING STILL IMAGES TO AN ALBUM EXITING DIGITAL PHOTO NAVIGATOR	
Playing Back and Handling Images (Windows [®])	
LOADING AN ALBUM	
DISPLAYING STILL IMAGES Displaying a selected still image Displaying a series of images Enlarging and reducing images	
ORGANIZING ALBUMS Selecting multiple still images Deleting unnecessary still images Copying still images	
SENDING IMAGES FROM AN ALBUM IN E-MAIL	
CREATING A WEB PAGE	22
CHANGING THE IMAGE SIZE OR PICTURE QUALITY Changing the image size Changing the picture quality, etc	24
RETRIEVING STILL IMAGES FROM AN ALBUM	
CREATING A LIST OF STILL IMAGES	27
CREATING A SLIDE SHOW OR AN ANIMATION	

Digital Photo Navigator (Macintosh)	29
STARTING DIGITAL PHOTO NAVIGATOR	30
Digital Photo Navigator window	
CAPTURING IMAGES	33
Capturing still images from tape	
Automatic Capture	
Changing the transfer speed	36
Changing the image size	
Changing the connecting port	
Changing the JLIP ID number	37
EXITING DIGITAL PHOTO NAVIGATOR	38
HANDLING THE CAPTURED IMAGES AFTER CAPTURING	39
Saving the captured image in other directory	39
Saving the captured image in another file format	39
Saving the captured image in another image size	
Saving the captured image after changing the field mode	
Appendix	41
TROUBLESHOOTING	42
INDEX	45

CAUTION:

- Operate this equipment according to the operating procedures described in this manual.
- Use only the provided CD-ROM. Never use any other CD-ROM to run this software.
- Do not attempt to modify this software.
- Changes or modifications not approved by JVC could void user's authority to operate the equipment.

How to handle a CD-ROM

- Take care not to soil or scratch the mirror surface (opposite to the printed surface). Do not write anything or put a sticker on either the front or back surface. If the CD-ROM gets dirty, gently wipe it with a soft cloth outward from the center hole using a circular motion.
- Do not use conventional disc cleaners or cleaning spray.
- Do not bend the CD-ROM or touch its mirror surface.
- Do not store your CD-ROM in a dusty, hot or humid environment. Keep it away from direct sunlight.
- You can find the latest information (in English) on the provided software program at our world wide web server at http://www.jvc-victor.co.jp/english/index-e.html
- Microsoft[®] and Windows[®] are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- Macintosh is a registered trademark of Apple Computer, Inc.
- Keyspan is a trademark of InnoSys Inc.
- Other product and company names included in this instruction manual are trademarks and/or registered trademarks of their respective holders.

Reading this document

This document consists of the following three sections and an Appendix. Before use, please read the Setup Guide for preparation.

■ Loading Still Images (Windows®)

This section explains how to capture images from the camcorder tape to the PC. This section also explains how to load still images into the album of the Digital Photo Navigator software.

Playing Back and Handling Images (Windows[®])

This section explains how to handle still images using the Digital Photo Navigator software. You can send still images by e-mail and store an album as a web page.

Digital Photo Navigator (Macintosh)

This section explains how to capture images from the camcorder tape to the PC.

Appendix

This appendix contains troubleshooting and index.

Loading Still Images (Windows®)

You can capture still images from the recorded camcorder tape or load still image files from the hard disk in the PC. The Digital Photo Navigator software allows you to store and view still images in a photo album format. The icons on the Digital Photo Navigator window have the same functions as the menus. In this section, almost all the procedures are explained using the icons.

Read this section if you are using a Windows® operating system.



6 EN

You can capture still images from the recorded camcorder tape, or load still image files from the hard disk in the PC. After capturing or loading images, create an album that contains a collection of still images.

Preparation

- Connect the camcorder to the PC with the PC connection cable.
 - Refer to "CONNECTIONS (Windows®)" (1) pg. 6) in the Setup Guide.
- 2 Select [Start] [Programs] [Digital Photo Navigator] – [Digital Photo Navigator 1.0]. Digital Photo Navigator starts.
 - Close any other programs running on the PC.
 - Disable any programs that run in the background, such as screen savers, e-mail applications, virus checkers, schedulers, etc.
 - Turn off file and printer sharing.



Capturing still images from tape


You can capture still images from the camcorder tape on the PC.

- Set the Power Switch on the camcorder to " **PLAY**". The camcorder is now on.
- **2** Click [Import].
- **3** Click [Camcorder]. The Controller window appears.

NOTE:

If the camcorder is not connected to the PC, the camcorder is turned off, or the camcorder is connected to any serial port other than COM1, the [JLIP Devices] dialog box appears.

- 1) Connect the camcorder to the PC with the PC connection cable.
 - Refer to "CONNECTIONS (Windows®)" (IF pg. 6) in the Setup Guide.
- 2) Set the Power Switch on the camcorder to " PLAY". The camcorder is now on.
- **3)** Select the appropriate setting for [Serial Port] depending on the port in use.
- 4) Click [Scan].
- 5) If the camcorder name [VCRCAMERA] appears, click [OK].



VCR ID:06 VCRCAMERA

Name

Camcorder VCBCAMERA

OK

Not Connected

Cancel

Scan No Device

No. ID Category

Scan


- 4 Click the ► button in the Controller window.
 Playback of the camcorder tape starts.
- **5** Click the Capture button when the desired image appears.
 - The image is transferred to the PC and thumbnail image appears to the right-hand side of the Digital Photo Navigator window.
- **6** Repeat steps **4** and **5** to capture additional images.
 - It is possible to capture or add up to two hundred images into an album.
- 7 Click [Export] after capturing is completed.
- 8 Click [Album].

The [Save As] dialog box appears.

9 Specify the location where you want to save the album, input the file name of the album, and then click [Save].


The album is saved.

- If you save an album for the first time after the software installation, a message appears and asks if you want to register the association of the file extension name "jia". Then, click [Yes].
- To exit Digital Photo Navigator, refer to "Exiting Digital Photo Navigator" (🖙 pg. 14).



EN

Digital P				
<u>File</u> Edit	Import E	sport <u>W</u> indow <u>H</u>	jelp	
Import	Export	001	002	003
Abum E-Mal	Image	004	005	006
Web Page	Movie	007	008	
Change Format				
Digital Pho	ito Navig	ator		
?	Do you i	extension name want to register	the association I	ociate with this program. now?



NOTES:

- Use only the operation buttons in the Controller window to control the camcorder. If you operate the camcorder with its own operation buttons, the appearance of the Controller window may not correspond to the status of the camcorder, or it may cause a malfunction to occur in Digital Photo Navigator.
- The Controller window may appear to still be operating the camcorder even after the videocassette automatically stops at the beginning or end of the tape. In this case, click the Stop (
) button in the Controller window before performing another operation.
- If an image is captured in the Pause or Slow Play mode, some noise may appear on the captured image. In this case, capture the image during normal playback.

Automatic Capture

You can automatically capture still images from the camcorder tape on the PC according to your preferences. There are 2 ways available: "Photo Capture" and "Interval Capture".

- Set the Power Switch on the camcorder to " **PLAN**". The camcorder is now on.
- 2 Click the ► button in the Controller window.
- **3** Click the Automatic Capture button. The camcorder enters still playback mode.



4 Go to steps in "Photo Capture" or "Interval Capture" below.

NOTES:

- Depending on your PC's specifications and operating environment, the points where images are captured may not match what was set in the preferences.
- If the videotape is damaged, the points where images are captured may not match what was set in the preferences.
- Automatic capture may not function properly if portions of the videotape are unrecorded.
- Automatic capture cannot be performed in the time code range from 00:00:00:00 to 00:00:30:00.
- Automatic capture stops when the number of images in the right-hand side of the Digital Photo Navigator window reaches 200 or the videotape ends.

Photo Capture

You can capture only snapshot images recorded on a tape.

- Select [Photo Capture] in the Automatic Capture window.
- **2** Set the number of images to be captured.
- **3** Click [OK]. The camcorder starts forward search and capturing is performed when each snapshot image is found out.
 - If you want to start the search from beginning of a tape, select [Rewind the tape] before clicking [OK].
- **4** Click [Export] after capturing is completed.
- 5 Click [Album].

The [Save As] dialog box appears.

6 Specify the location where you want to save the album, input the file name of the album, and then click [Save].

The album is saved.

- If you save an album for the first time after the software installation, a message appears and asks if you want to register the association of the file extension name "jia". Then, click [Yes].
- To exit Digital Photo Navigator, refer to "Exiting Digital Photo Navigator" (EP pg. 14).

NOTE:

Photo Capture may not function properly when, for example, the camcorder tape includes snapshot images recorded after the recording speed was changed, or when snapshot images were continuously recorded. In these cases, capture images by performing the steps in "Capturing still images from tape" (🖙 pg. 6).

 Photo Capture Rewind the tape 	Number of Images
C Interval Capture	OK
min. sec.	Cancel

Number of images



Interval Capture

You can capture images at specified intervals. This function is useful for summarizing the contents of a tape, or for watching time-lapse movies using the slide show.

- Select [Interval Capture] in the Automatic Capture window.
- **2** Set the number of images to be captured.
- **3** Set the length of the interval (in minutes and seconds).
- 4 Click [OK].
- **5** Click [Export] after capturing is completed.
- **6** Click [Album]. The [Save As] dialog box appears.
- **7** Specify the location where you want to save the album, input the file name of the album, and then click [Save].

The album is saved.

- If you save an album for the first time after the software installation, a message appears and asks if you want to register the association of the file extension name "jia". Then, click [Yes].
- To exit Digital Photo Navigator, refer to "Exiting Digital Photo Navigator" (Dep pg. 14).

NOTE:

This function doesn't work if there is no time code recorded on the videotape or if the recording time is shorter than 1 minute.

CAPTURING IMAGES (cont.)





Changing the transfer speed

The default setting is 115200bps. Depending on the PC in use, transmission errors may occur. In this case, change to a lower serial speed setting, however, the rate of image transfer will be slower.

- Right-click the Controller window and then, in the menu that appears, click [Device Setting]. The [JLIP Devices] dialog box appears.
- 2 Select the desired setting for [Picture Transfer Rate].
- 3 Click [OK].



Changing the ID number

When two or more camcorders are connected to the PC, be sure to change the ID number between 1 and 99 for the connected camcorder that there is no duplication of ID numbers. The default ID number is 06.

- Right-click the Controller window and then, in the menu that appears, click [Device Setting]. The [JLIP Devices] dialog box appears.
- **2** Right-click the number in the list box, then click [Change ID].
- 3 Input the ID number and press Enter key.
- 4 Click [OK].

NOTE:

Refer to the Instruction Manual of the connected camcorder for details on changing the ID number of a camcorder.

JLIP Devices	×
Serial Port Picture Transfer Rate COM1 115200	
Selected Device VCR ID:06 VCRCAMERA	Select
Scan No Device	Select
No. ID Category Name	Scan
Not Connected	
1 06 Damcorder VCRCAMERA	

12 en

You can load the still image files (bitmap or JPEG format) from the hard disk in the PC to an album.

- Start Digital Photo Navigator.
- 2 Click [Import].
- **3** Click [Image]. The [Open] dialog box appears.
- **4** Open the folder that contains the desired still images.



- **5** Select the desired still image files and click [Open]. The still images are added to the right-hand side of the Digital Photo Navigator window.
 - You may select more than one file.
 - You can also add files by dragging and dropping them in the Digital Photo Navigator window.
- **6** Add additional still images as desired by repeating steps **3 5**.

7 Click [Export].

- 8 Click [Album]. The [Save As] dialog box appears.
- **9** Specify the location where you want to save the album, input the file name of the album, and then click [Save].

The album is saved.

- If you save an album for the first time after the software installation, a message appears and asks if you want to register the association of the file extension name "jia". Then, click [Yes].
- To exit Digital Photo Navigator, refer to "Exiting Digital Photo Navigator" (27 pg. 14).

import	nort Export		002 005 008	03 066
Digital Photo	he file extr	ension name 'i	ia' doesn't assoc ne association no	iate with this program.

Νo

Yes

14 en

- Click the [File] menu and then click [Exit].
 If you have already saved an album, a confirmation message appears. Then, go to step 2.
 - If you have not saved an album after capturing or loading still images, a confirmation message appears. To save an album, click [Yes]. The [Save as] dialog box appears. Specify the location where you want to save the album, input the file name of the album, and then click [Save]. A confirmation message appears. Then, go to step 2. To exit Digital Photo Navigator without saving an album, click [No]. A confirmation message appears. Then, go to step 2.

2 Click [Yes].

Digital Photo Navigator closes.



Digital Photo Navig	ator 🗵
😲 Close Digita	I Photo Navigator?
Yes	No

Playing Back and Handling Images (Windows®)

This section explains how to handle still images using Digital Photo Navigator.

You can send still image files as an e-mail attachment and store an album as a web page. Be sure to read "Loading Still Images (Windows[®])" before reading this section.

The icons on the Digital Photo Navigator window have the same functions as the menus. In this section, almost all the procedures are explained using the icons.

Read this section if you are using a Windows® operating system.



16 en

- 1 Start Digital Photo Navigator.
- 2 Click [Import].
- **3** Click [Album]. The [Open] dialog box appears.

4 Open the folder where the album was saved.

5 Click the desired album file, and then click [Open]. The contents of the album are displayed in the right-hand side of the Digital Photo Navigator window.

NOTES:

- You can also open the album file by dragging and dropping it in the Digital Photo Navigator window.
- If an album is currently open, a confirmation message appears.
 - If you want to open the newly selected album instead of the one already opened, click [Yes]. If you have not saved the album already opened, a confirmation message appears. If you want to save the album, click [Yes]. If you do not want to save the album, click [No].
- Digital Photo Navigator
 Image: Second seco
- If you want to add still images from the newly selected album to the album already opened, click [No].





Displaying a selected still image

You can select for display any of the still images that are displayed in the right-hand side of the Digital Photo Navigator window.


1 Double-click the still image to be displayed. The [Image Viewer] window appears, and the selected image is displayed.





Displaying a series of images

To display a series of images in "slide show" fashion, click the 🕨 button in the [Image Viewer] window. You can also move through the images manually in either direction by clicking the 📶 and 🔟 buttons.



To adjust the speed of the slide show, right-click the [Image Viewer] window and then, in the menu that appears, click [Slide show] – [Setting Interval Time]. Set the length of the interval (in seconds), and then click [OK].

NOTE:

The interval for a slide show is a little longer than the setting because of display processing time.

Enlarging and reducing images


The following procedure describes how to change the display size of a still image.

- Drag the corner of the [Image Viewer] window to change the size of the window to the desired display size.
- 2 Right-click the [Image Viewer] window and then, in the menu that appears, click [Zoom] [Auto]. The size of the still image is automatically enlarged or reduced to fit the window, and the display magnification (enlargement/ reduction percentage) indicated in the title bar of the window changes accordingly.

Other enlargement/reduction functions

In addition to adjusting the size of the image to the size of the window, the display size of a still image can also be changed by the methods described below. Each of these functions can be selected by right-clicking the [Image Viewer] window.

- [Zoom] [Real Size]: Displays the image in its original size (display magnification of 100%).
- [Zoom] [Zoom In]: Displays the image at twice its current display magnification (up to 400%).
- [Zoom] [Zoom Out]: Displays the image at half its current display magnification (up to 20%).



ORGANIZING ALBUMS


Whenever necessary, you can delete or copy still images that you have added to an album. The procedure described below only affects the still image in the album. It does not affect the original file of the still image that was added to the album.

Selecting multiple still images

To delete or copy multiple still Images at once, select them in advance. You can also select all still images in the album.

Selecting still images continuously

Click still images while holding down the Shift key.



Selecting still images one by one

Click still images while holding down the Ctrl key.



Selecting all of the still images

Click [Select All] in the [Edit] menu.

<u>E</u> dit	
Cuţ	Ctrl+X
<u>С</u> ору	Ctrl+C
<u>P</u> aste	Ctrl+V
Delete	
Select <u>A</u> ll	Ctrl+A
Inverse Selection	î

Deleting unnecessary still images


- Click the still image that you want to delete, and then click [Delete] in the [Edit] menu. A confirmation message appears.
- **2** Click [Yes]. The selected still images are deleted.



No

Copying still images

Click the still image that you want to copy, and then click [Copy] in the [Edit] menu.




Yes

- **2** Click the image that is located right after the insertion point.
 - To add the images at the end of the album, click the blank space in the right-hand side of the window.
- **3** Click [Paste] in the [Edit] menu. The copied still images are inserted right before the selected image.

NOTE:

You can delete, copy or paste an image also by right-clicking it.



Insertion point

Still images in an album can be sent as an e-mail attachment.

Click the still image that you want to send, and then click [E-Mail].

The new message window in your e-mail program appears, and the still image file is registered as an attachment.

NOTES:

- Depending on an e-mail software, a new message window may not open when the [E-Mail] button is clicked.
- Depending on an e-mail software, settings such as "Set as MAPI client" or "Used by MAPI application" are necessary.
- The maximum number of messages that can be created at once is three.



<mark>BNew Me</mark> Ele <u>E</u> d		Inset	Fgrmat	Tools	Messa	pe <u>H</u> elp						- 0
드) Send	No.	L	Paste		$\underline{\mathfrak{G}}_{\checkmark}$ Check	sec Speling	() Altach	J.Priority	-	⊡g Sign	Encrypt	Offine
[2] Τα												
Subject									_			
Attach:	JVMO	0004.JPG	(108 KB									
	_	E.	V	E. E	. <i>I</i> J	LA.	E E -	定 疟	I.B.	8.8		- 0. 2
	_							9 9 <u>9</u>				
-												

You can save the contents of an album in HTML format. This is useful in the following instances:

When creating a web page: When distributing an album: You can create a web page that features a collection of photos. You can create an album in a format that can be displayed by a web browser. This is useful if you want to distribute the album on CD-R, etc.

- Select the still images that you want to save in HTML format.
 - To select more than one still image, hold down the Shift key or the Ctrl key while clicking the images.
 - To select all of the still images, click [Select All] in the [Edit] menu.
- **2** Click [Web Page].

The [Web Page] dialog box appears.



3 Set the following items when necessary.

- [Title]: This will be the title of the web page.
- [Font Color]: This specifies the color of the title text.
- [Back Color]: This specifies the background color of the web page. (Specify a color other than the font color.)
- [Limit horizontal size of the images]: This allows you to specify the maximum width of the image when displayed by a web browser. (Set the number of pixels much smaller than the width of the PC's display.)

Web Page	×
Title	
My Pictures	Font Color
Image	
Limit horizontal size of the images	
Maximum pixels 480	
OK Cancel	J

4 Click [OK], specify the save location, and then click [Save].

The HTML file is saved, and a folder with the same name is saved at the same time. A confirmation message appears next, asking whether to display the web page.

5 Click [Yes].

The web browser opens, and the HTML file that was created is displayed.

• Click on an image on the web page to enlarge it.

page001.htm page001



What Next?

You can also view an HTML file through the web browser by double-clicking the HTML file. You can upload the HTML file to your home page, or save it on a CD-R or some other media and distribute it. Always handle HTML files and folders as a set. Without its folder, an HTML file cannot be viewed by a web browser.

NOTES:

- For more details on how to create a home page, consult your Internet service provider's web site or one of the many reference books available.
- Use third-party home page creation software or similar software to edit HTML files.

Changing the image size

This procedure describes how to change the size of an image that has been loaded into Digital Photo Navigator. This procedure is used to reduce the size of an image that is being attached to an e-mail or saved in an album.

- Select the still image to be changed.
 - To select more than one still image, hold down the Shift key or the Ctrl key while clicking the images.
 - To select all of the still images, click [Select All] in the [Edit] menu.
- 2 Click [Change Format]. The [Image Format] dialog box appears.



3 Select one of the following items:

- [Expansion/Reduction]: Set any desired image size in the [Width] and [Height] fields. If the [Keep aspect ratio] check box is not selected (off), both [Width] and [Height] fields can be changed.
- [Generic Size]: Select the size from a list of generic sizes.
- [PDA Size]: This is an image size (160 x 160) that can be displayed on most PDAs.
- 4 Click [OK].
 - If you select more than one still image in step 1, a confirmation message appears.
 - If you want to apply the same format to all images, click [Yes].
 - If you do not want to apply the same format, click [No]. The first image is saved. Then, select the image size for each image.

The image size is changed to the selected size. If the vertical-to-horizontal ratio was changed, the blank spaces are shown as black.



Changing the picture quality, etc.

In addition to changing the size of an image, it is also possible to rotate images, change or correct the quality of an image, and change the file format of an image. The role of each setting is described in more detail below.

[90 degrees Rotation]

If you hold the camcorder sideways when recording an image, you can create an image that is taller than it is wide. Because this still image will be displayed sideways, use this function to rotate the image 90 degrees to the portrait orientation.

[None]: No correction

[Clockwise]: Rotates the image 90 degrees clockwise. [Counterclockwise]: Rotates the image 90 degrees counterclockwise.



[Image Correction (DV)]

Sometimes, when you shoot a subject that is moving very quickly, the resulting image will be blurred. It is possible to correct this blurring to a certain extent. Because the optimal type of correction depends on the still image, we recommend making a copy of the image and experimenting with the copy. It is not possible to correct for blurring caused by shaking the camera while shooting.

[None]: No correction

[Movement]: Corrects only the blurred portions.

[Field]: Corrects blurring more quickly than [Movement].

[Format]

You can select the file format of an image.

[JPEG]: This is the format that is typically used on the Internet. This format has a smaller file size. [BITMAP]: This is the standard Windows[®] image format (BMP). Many applications can use this format.

[JPEG Quality]

This setting is available when JPEG was selected in the [Format] field. Moving the slider to the left makes the file smaller. Moving the slider to the right results in less deterioration in the image quality. The initial setting is 75.

NOTES:


- When [JPEG] is selected in the [Format] field, the quality of the image deteriorates slightly each time that [OK] is clicked for the [Image Format] dialog box. To restore the original image quality, reload the original still image file.
- The setting in the [Image Correction (DV)] field has an effect only when the still image was shot with a digital video camera.
- When you shoot a subject that is moving too quick, some blurring cannot be corrected with the setting in the [Image Correction (DV)].
- When [Field] is selected in the [Image Correction (DV)] field, the quality of the original image deteriorates.
- To confirm the file size, right-click the still image and then select [Properties].

You can retrieve still images from an album and save them as a file.

- Select the still image to be retrieved.
 - To select more than one still image, hold down the Shift key or the Ctrl key while clicking the images.
 - To select all of the still images, click [Select All] in the [Edit] menu.
- **2** Click [Image].

The [Image Format] dialog box appears.





3 Change the image format as desired. (1) pg. 24, 25) Then, click [OK].

The [Save As] dialog box appears.

4 Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

- If you select more than one still image in step 1, a confirmation message appears.
 - If you want to save all images with the same image format and their default name, click [Yes]. The [Auto Save Result] dialog box appears. Then, click [OK].
 - If you want to set the image format and input file name for each image, click [No]. The first image is saved. The [Image Format] dialog box appears for the second image. Repeat steps 3 and 4 as many times as necessary.

CREATING A LIST OF STILL IMAGES


You can arrange multiple still images together and save them in a single still image file.

- Holding down the Shift key or the Ctrl key, select the still images that are to be added to the list.
- **2** Click [Multi Image]. The [Multi Image] dialog box appears.



-Back Color Save Close







- **3** Select the number of partitions.
 - Either 4, 9, or 16 partitions may be selected.
- **4** Click [Back Color], select the color for the overall background, and then click [OK].

5 Change the positions of the still images as desired.

- Deleting an image: Right-click the still image and then select [Delete].
- Adding an image: Drag an image from the right-hand side of the Digital Photo Navigator window to the [Multi Image] dialog box.

6 Click [Save].

The [Image Format] dialog box appears.

7 Change the image format as desired. (**I** pg. 24, 25) Then, click [OK]. The [Save As] dialog box appears.

8 Specify the location where you want to save the file, input the file name, and then click [Save]. The still image list file is saved.

You can create a slide show or an animation in which a series of still images are displayed, and then save those images as a movie file (extension ".avi").

[Slide Show]: Still images are displayed for several seconds each, one at a time.

[Animation]: Several still images are displayed per second. We recommend that you select a series of still images that create the appearance of continuous movement.

- **1** Holding down the Shift key or the Ctrl key, select several still images.
- 2 Click [Movie].

The [Movie Settings] dialog box appears.





- **3** Select either [Slide Show] or [Animation], which ever is desired.
 - For a slide show, set the length of the interval (in seconds).
 - For an animation, set the number of displayed frames (images) per second.

4 Set the following items when necessary.

- [Image Size]: Select the size of the movie file.
- [Compressor]: Select the type of compressor.
- [Back Color]: This item is used if the aspect ratio of the images is not 4:3.
- 5 Click [OK].

The [Save As] dialog box appears.

- **6** Specify the location where you want to save the file, input the file name, and then click [Save]. The movie file is saved, and a confirmation message that asks if you want to play the movie now appears.
- 7 Click [Yes].

The movie file is played back.

NOTES:

- If you change the [Compressor] item, make sure that the playback system supports that type of compressor.
- Depending on the selected type for [Compressor], a movie file cannot be created.
- In some cases, the settings in the [Video Compression] dialog box are invalid.

Digital Photo Navigat	or 🛛 🕅
Po you want to	play the Movie now?
	No

Digital Photo Navigator (Macintosh)

You can capture still images from the recorded camcorder tape. The Digital Photo Navigator software allows you to store and view still images in the hard disk of the PC.

The icons on the Digital Photo Navigator window have the same functions as the menus. In this section, almost all the procedures are explained using the icons.

Read this section if you are using a Macintosh operating system.



30 en

Preparation

- Connect the camcorder to the PC with the PC connection cable and the USB PDA ADAPTER.
 - Refer to "CONNECTIONS (Macintosh)" (IF pg. 9) in the Setup Guide.
 - Never disconnect the PC connection cable or the USB PDA ADAPTER while Digital Photo Navigator is running.
- **2** Open the [Digital Photo Navigator 1.0] folder.
 - Close any other programs running on the PC.
 - Disable any programs that run in the background, such as screen savers, e-mail applications, virus checkers, schedulers, etc.
 - Turn off file and printer sharing.
- **3** Double-click the [Digital Photo Navigator] icon.

The port selection dialog box appears.

Digital Photo Navigator 1.0




4 Select [Keyspan USB DB9]* for connecting port and click [OK].

Digital Photo Navigator starts.

- If you start Digital Photo Navigator at the first time, a "pictures000" folder for saving images is automatically created in the [Digital Photo Navigator 1.0] folder.
- * The name of connecting port may differ depending on the driver version.

Port selecti				
	ect conneting "OK" button.	port.		
	Keyspan	USB DB9	•	ОК
	ected to serial ct it and launc			
				Quit

Digital Photo Navigator window



NOTES:

- Use only the operation buttons to control the camcorder. If you operate the camcorder with its own operation buttons, the appearance may not correspond to the status of the camcorder, or it may cause a malfunction to occur in Digital Photo Navigator.
- If an image is captured in the Pause or Slow Play mode, some noise may appear on the captured image. In this case, capture the image during normal playback.

Image selection dialog box

If the image number button is clicked, the image selection dialog box appears. Select the desired folder, input the desired image number and click [OK]. The specified image is displayed. This function is convinient when you open an already captured image to save it in other directory or in another file format, or change the image size and save it with different name. (IF pg. 39, 40)

Select folder : 🖌 pictures000
Image number :
Cancel OK

Image display

Displays the captured image. To display the [Real size image] window, click the image display.

[Real size image] window

You can view the captured image in real size.



Changing the display size of the [Real size image] window

Select the desired setting from a list of generic sizes of [Image size] in the [File] menu.

File	_
Save as PICT	1
Save as JPEG	
Save as other	
lmage size 🕨	✓ 640x480
Field mode 🕨 🕨	320x240
Ouit ೫0	160x120
	80x60

Capturing still images from tape


You can capture still images from the camcorder tape on the PC.

- Set the Power Switch on the camcorder to " **PLAY**". The camcorder is now on.
- 2 Click the Play (►) button. Playback of the camcorder tape starts.
- **3** Click the Capture button when the desired image appears.

The image is transferred to the PC and it is displayed in the image display after transferring.

- The image file is automatically saved as JPEG format file in the folder "pictures000".
- The first image file is named "image001" and the number increases one by one each time new image is captured.

4 Repeat steps 2 and 3 to capture additional images.



Automatic Capture

You can automatically capture still images from the camcorder tape on the PC according to your preferences. There are 2 ways available: "Photo Capture" and "Interval Capture".

NOTES:

- Depending on your PC's specifications and operating environment, the points where images are captured may not match what was set in the preferences.
- If the videotape is damaged, the points where images are captured may not match what was set in the preferences.
- Automatic capture may not function properly if portions of the videotape are unrecorded.
- Automatic capture cannot be performed in the time code range from 00:00:00:00 to 00:00:30:00.
- Automatic capture stops when the number of images in the folder for saving images (such as "pictures001") reaches 100 or the videotape ends.

Preparation: Specifying the location where you want to save the images

Select [Auto save settings...] in the [Capture] menu. The [Data save settings] dialog box appears.



2 Specify the location where you want to save the images. You have 2 choices.

When saving the images in a new folder:

Click [Separating folder].

Each time Automatic Capture is performed, a new folder named "picturesXXX" (The number increases from 001 and up to 099) is automatically created in the [Digital Photo Navigator 1.0] folder. The images are saved in the new folder.

When saving the images in the "pictures000" folder: Click [Folder fixed].

 \bullet You can select the size of an image to be captured. (127 pg. 37)

3 Click [OK].

After preparations, perform the steps in "Photo Capture" (IP pg. 35) or "Interval Capture". (IP pg. 36)



Photo Capture

You can capture only snapshot images recorded on a tape.


Click the Photo Capture button. The [Photo scene search capture setting] dialog box appears.


- **2** Select the tape position to start capturing.
 - To start capturing from the beginning of the tape: Click [Beginning of tape].
 - To start capturing from the current tape position: Click [Current position].
- **3** Select how to stop capturing.
 - To capture all the Snapshots to the end of the tape: Click [End of tape].
 - To specify the number of images to be captured: Click [Reserved times] and then select the number of images.
- **4** Click [Go ahead].

NOTE:

Photo Capture may not function properly when, for example,

the camcorder tape includes snapshot images recorded after the recording speed was changed, or when snapshot images were continuously recorded. In these cases, capture images by performing the steps in "Capturing still images from tape" (127 pg. 33).





36 en

Interval Capture

You can capture images at specified intervals. This function is useful for summarizing the contents of a tape, or for watching time-lapse movies using the slide show.

- Click the Interval Capture button. The [Interval capture setting] dialog box appears.
- **2** Select [ON (control by tape counter)] for VCR control.

- **3** Select the length of the interval (in seconds or minutes).
- **4** Select the tape position to start capturing.
 - To start capturing from the beginning of the tape: Click [Beginning of tape].
 - To start capturing from the current tape position: Click [Current position].
- **5** Select how to stop capturing.
 - To stop capturing at the end of tape: Click [End of tape].
 - To specify the number of images to be captured: Click [Reserved times] and then select the number of images.
- **6** Click [Go ahead].

NOTES:

- This function doesn't work if there is no time code recorded on the videotape or if the recording time is shorter than 1 minute.
- [OFF] in the [VCR control] cannot be selected with digital video cameras.



Interval capture setting :	
Interval	_3
VCR control	
ON (control by tape counter)	2
○ OFF (control by timer)	- 2
Start position	
Ø Beginning of tape	
Current position	- 4
Repeat	
🔾 End of tape	_ 5
Reserved times : 1	
Cancel Go ahead	L 6
	U

Changing the transfer speed

The default setting is 57600bps. Depending on the PC in use, transmission errors may occur. In this case, change to a lower serial speed setting, however, the rate of image transfer will be slower.

- Select [Transfer speed...] in the [Device] menu.
- **2** Select the desired setting.
- 3 Click [OK].

Device	
Connecting Port	
Transfer speed	
JLIP ID	
	-
Transfer speed: 57600bps 🗕 🌲	—2
Cancel OK	3
	-

Changing the image size

You can select the size of an image to be captured.

Select [Auto save settings...] in the [Capture] menu. The [Data save settings] dialog box appears.

2 Select the image size from a list of generic sizes.

3 Click [OK].

NOTE:

You can also change the size of an image after capturing. (IF pg. 40) Note that if an image is enlarged to the size larger than its original, it will take on a mosaic appearance.

Interval capture ... Seeking capture ... Auto save settings ... Data save settings: Image Save size (pixel): 640 x 480 ÷ 2 Place Place © Separating folder © Folder fixed Cancel OK 3

Capture

Take a single image

Changing the connecting port

If you connect two or more serial devices to the PC, select the connecting port depending on the camcorder in use.

- Select [Connecting Port...] in the [Device] menu.
- **2** Select the desired connecting port.
- 3 Click [OK].

Device	
Connecting Port	
Transfer speed	
JLIP ID	
Select connecting port : 🛛 Keyspan USB DB9 🗢	+2
Cancel OK -	3


Changing the JLIP ID number

When two or more camcorders are connected to the PC with serial devices, be sure to change the ID number between 1 and 99 for the connected camcorder that there is no duplication of ID numbers. The default ID number is 6.

- Select [JLIP ID...] in the [Device] menu.
- **2** Input the desired JLIP ID number between 1 and 99.
- **3** Click [OK].

NOTE:

Refer to the Instruction Manual of the connected camcorder for details on changing the ID number of a camcorder.



38 en

EXITING DIGITAL PHOTO NAVIGATOR

Select [Quit] in the [File] menu. Digital Photo Navigator closes.

File



Saving the captured image in other directory

- Right after capturing an image or displaying the desired image in the image display (☞ pg. 31, 32), click the Save As button. The [Save] dialog box appears.
- 2 Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

Saving the captured image in another file format

PICT format

- Right after capturing an image or displaying the desired image in the image display (IFP pg. 31, 32), select [Save as PICT...] in the [File] menu. The [Save] dialog box appears.
- **2** Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

Any format other than JPEG or PICT

- Right after capturing an image or displaying the desired image in the image display (IF pg. 31, 32), select [Save as other...] in the [File] menu. The [Save] dialog box appears.
- 2 Select the desired file format.
- **3** Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

File	
Save as PICT	
Save as JPEG	
Save as other	
Image size	•
Field mode	►
Quit %	Q





-Save As

Saving the captured image in another image size

- Right after capturing an image or displaying the desired image in the image display (IFP pg. 31, 32), select the desired setting from a list of generic sizes of [Image size] in the [File] menu.
- **2** Click the Save As button. Select [Save as PICT...] or [Save as other...] in the [File] menu.
- **3** Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

NOTES:

- You can check the selected image size with the [Real size image] window. (
 pg. 32) However, close the [Real size image] window before saving an image.
- Note that if an image is enlarged to the size larger than its original, it will take on a mosaic appearance.


Saving the captured image after changing the field mode


Normally, captured images are saved in [Dual field mode]. When you shoot a subject that is moving quickly, it is recommended to select [Single field mode] and save the image.

- Right after capturing an image or displaying the desired image in the image display (\$\varphi\$ pg. 31), select [Single field mode] of [Field mode] in the [File] menu.
- 2 Click the Save As button. Select [Save as PICT...] or [Save as other...] in the [File] menu.
- **3** Specify the location where you want to save the file, input the file name, and then click [Save]. The image file is saved.

NOTES:

- When you shoot a subject that is moving too quick, some blurring cannot be corrected.
- When [Single field mode] is selected, the quality of the original image deteriorates.





Appendix

This appendix contains troubleshooting and index.

Windows®

42 en

SYMPTOM	CORRECTIVE ACTION	REFER TO:
Although the PC connection cable is connected, Digital Photo Navigator cannot control the camcorder.	 Make sure that the AC Adapter is connected to the camcorder and that the power is on. Make sure that the PC connection cable is connected securely. 	Setup Guide (≌ pg. 6)
The connected camcorder cannot be detected. The COM port cannot be set.	 Make sure that the AC Adapter is connected to the camcorder and that the power is on. Make sure that the PC connection cable is connected securely. If it is still not detected after clicking [Scan] in the [JLIP Devices] dialog box two or three times, try turning off your PC and camcorder. Confirm the connection 	Setup Guide (ﷺ pg. 6) pg. 6 pg. 11 Setup Guide
	 between them then turn them both back on. Confirm that the [JLIP Devices] dialog box is operating properly after clicking [Scan]. If you are using a built-in modem or IrDA, the RS-232C 	(☞ pg. 6) pg. 6 pg. 11
	COM port may occupied. In this case, right-click [My Computer], then select [Properties]–[System Properties]– [Device Manager]. Click [Ports (COM & LPT)] to confirm which COM port is available. If all the COM ports are occupied, set the COM port used by the modem or IrDA driver to [Invalid].	_
	 If a USB or Digital Still Camera driver is installed on your PC, you may not be able to use the RS-232C port. Depending on your PC's specifications, you may need to change the BIOS settings. 	_
Cannot copy or save files.	 Make sure that there is enough free space available in the drive where you are trying to copy or save a file. Make sure that the drive where you are trying to copy or save a file is not write-protected. Make sure that a file with the same name does not already exist where you are trying to copy or save a file. 	_

Windows[®] (cont.)

SYMPTOM	CORRECTIVE ACTION	REFER TO:
Cannot load still images into Digital Photo Navigator.	 Sometimes the format of the still image data prevents it from being loaded into Digital Photo Navigator. Use other graphics drawing or processing software to convert the file to either bitmap format or JPEG format. Make sure that there is enough free space available in the drive in which Digital Photo Navigator is installed. 	_
Still images have a mosaic appearance.	 When a small image is loaded and enlarged, it will take on a mosaic appearance. If an image is saved with a lower JPEG quality or if the format of the image is changed, it will take on a mosaic appearance. 	pg. 18 pg. 25
The colors displayed on the PC are odd.	• Images will not be displayed correctly if the display is set for 256-color (or fewer) display.	—
Automatic capture does not function.	 This function may not operate correctly sometimes depending on your PC's specifications and operating environment. This may occur if correct data is not being transmitted due to damage on the videotape. This may occur if a tape recorded in the LP mode is played back on a different camcorder. Play videotapes using the camcorder they were recorded on. There may be software running in the background. Confirm that there are no programs running in the background that may be using the processor at the same time as Digital Photo Navigator. 	_
Communication error occurs in capturing images. (Capturing is interrupted and camcorder does not function properly.)	• If the PC connection cable is not connected properly, communication may be interrupted and error occurs. Disconnect the AC Adapter from the camcorder, connect the PC connection cable properly, and then perform capturing again.	Setup Guide (🖙 pg. 6)

NOTE:

When using a laptop PC, operation may be interrupted by a warning when the battery is nearly exhausted.

- If there is software which monitors the status of the battery running in the [StartUp] folder...
- Close the application, or delete/move its icon from the [StartUp] folder and reboot your PC.
- If you are using your PC's power management function... Right-click the [My Computer] icon, then select [Properties]–[System Properties]–[Device Manager]– [System Devices]–[Advanced Power Management Support]. Desactivate the power management function.

44 EN

Macintosh

SYMPTOM	CORRECTIVE ACTION	REFER TO:
Although the PC connection cable is connected, Digital Photo Navigator cannot control the camcorder.	 Make sure that the AC Adapter is connected to the camcorder and that the power is on. Make sure that the PC connection cable is connected securely. 	Setup Guide (🖙 pg. 9)
Cannot copy or save files.	 Make sure that there is enough free space available in the drive where you are trying to copy or save a file. Make sure that the drive where you are trying to copy or save a file is not write-protected. Make sure that a file with the same name does not already exist where you are trying to copy or save a file. 	_
Automatic capture does not function.	 This function may not operate correctly sometimes depending on your PC's specifications and operating environment. This may occur if correct data is not being transmitted due to damage on the videotape. This may occur if a tape recorded in the LP mode is played back on a different camcorder. Play videotapes using the camcorder they were recorded on. There may be software running in the background. Confirm that there are no programs running in the background that may be using the processor at the same time as Digital Photo Navigator. 	Ι
Communication error occurs in capturing images. (Capturing is interrupted and camcorder does not function properly.)	• If the PC connection cable is not connected properly, communication may be interrupted and error occurs. Disconnect the AC Adapter from the camcorder, connect the PC connection cable properly, and then perform capturing again.	Setup Guide (☞ pg. 9)

INDEX

Windows®

Α

Adding still images	to an album	12
Automatic Capture		8

С

Capturing still images from tape	6
Changing the ID number	
Changing the image size	24
Changing the picture quality, etc	25
Changing the transfer speed	
Controller window	8
Copying still images	20
Creating a list of still images	27
Creating a slide show or an animation	
Creating a web page	

D

Deleting unnecessary still images20
Displaying a selected still image17
Displaying a series of images17

E

Enlarging and reducing images	
Exiting Digital Photo Navigator	14

Interval Capture	10
L Loading an album	16
P Photo Capture	9
R Retrieving still images from an album	26

S

Macintosh

Α

Any format other than JPEG or PICT	39
Automatic Capture	

С

Capturing still images from tape	33
Changing the connecting port	37
Changing the image size	
Changing the JLIP ID number	
Changing the transfer speed	

D

Digital Photo	Navigator window		1
---------------	------------------	--	---

E

Exiting D	Digital	Photo	Navigator	
-----------	---------	-------	-----------	--

I

Image display	
Image selection dialog box	
Interval Capture	

Р

Photo Capture	35
PICT format	

S

Saving the captured image after
changing the field mode40
Saving the captured image in another
file format
Saving the captured image in another
image size40
Saving the captured image in other
directory





M2D2 NON DSC 1101 HOV*ID

